

Scaling and Crossover Phenomena

The correlation length ξ is the only **characteristic length scale** in percolation. Above p_c , ξ is finite, and we expect different behavior on length scales $r < \xi$ and $r > \xi$.

We present a **scaling theory** for the crossover behavior in several quantities such as P_∞ , $M(r)$, $M(\ell)$, $R(\ell)$. Assume the scaling ansatz

$$P_\infty \sim (p - p_c)^\beta G(r/\xi) \sim \xi^{-\beta/\nu} G(r/\xi)$$

The scaling function G describes the crossover from $r/\xi \ll 1$ to $r/\xi \gg 1$. To obtain the expected results

$$P_\infty \sim (p - p_c)^\beta \quad \text{for } r \gg \xi \quad \text{and} \quad P_\infty \sim r^{d_f} / r^d \quad \text{for } r \ll \xi$$

in the two limits, we must require that

$$G(x) \sim \begin{cases} x^{d_f - d}, & x \ll 1 \\ \text{const}, & x \gg 1 \end{cases}$$

Thus, we find a unique function for $P_\infty(r, \xi)$ as a function of ξ and r

Scaling and Crossover Phenomena

We also determine how the mean mass M of the infinite cluster scales with r and ξ above p_c .

Since $M \sim r^d P_\infty(r, \xi)$, the mean mass of the infinite cluster scales as

$$M \sim r^{d-\beta/\nu} H(r/\xi), \quad H(x) = x^{\beta/\nu} G(x)$$

Since

$$G(x) \sim \begin{cases} x^{d_f-d}, & x \ll 1 \\ \text{const}, & x \gg 1 \end{cases}$$

we recover $M \sim r^{d_f}$ for $r < \xi$ and $M \sim r^d$ for $r > \xi$.

Finite Size Scaling

The dependence critical properties near p_c and p_c itself on the system size L

We had the scaling for
$$P_\infty \sim \xi^{-\beta/\nu} G(L/\xi) \sim \begin{cases} \xi^{-\beta/\nu} & L \gg \xi \\ L^{-\beta/\nu} & L \ll \xi \end{cases}$$

We expect similar scaling for other properties:

In general for property $Y(L,p)$ we expect

$$Y(L, p) \sim \xi^{-y/\nu} F_1(L/\xi) \sim \begin{cases} \xi^{-y/\nu} & L \gg \xi \\ L^{-y/\nu} & L \ll \xi \end{cases}$$

From which follows:

$$Y(L, p) \sim (p - p_c)^y F_2((p - p_c)L^{1/\nu}) \sim L^{-y/\nu} F_3((p - p_c)L^{1/\nu})$$

Finite Size Scaling

- If we calculate Y exactly at $p=p_c$ as a function of L we can get the exponent γ / ν

- Example $P_\infty(p_c, L) \sim L^{\beta/\nu}$; $M(p_c, L) \sim L^{d-\beta/\nu}$

- If ν is known we find γ .

Example $d=1$: we use $S(L, p) = L^{\gamma/\nu} f_s((p - p_c)L^{1/\nu})$

We showed that for $L \rightarrow \infty$

The mean cluster size $S = \frac{1+p}{1-p} \sim \xi \Rightarrow \gamma = \nu$

For $p=1$ and finite L , a single cluster exist $S=L$

Thus $\frac{\gamma}{\nu} = 1$ From which follows $\gamma = \nu = 1$

p_c in Finite Systems

For L finite there is a **finite** probability to find a spanning cluster at any finite p .

E.g., in $d=1$: The probability to find a cluster of size L is $\phi_p(L) = p^L = e^{-L/\xi}$
Which is finite for all p !!

If $L < \xi$ the prob. is greater than $1/e$


$L > \xi$ the prob. is smaller than $1/e$

For $L \rightarrow \infty$ we expect $\emptyset=0$ below p_c and $\emptyset=1$ above $p_c \rightarrow$ Step function

In $d=1$ $\emptyset=0$ for $p < 1$ and $\emptyset=1$ for $p=1$.

p_c in Finite Systems

For L finite use expect:



Since $\phi_p(L)$ is approaching a step function for $L \rightarrow \infty$, we define an effective threshold p^* when $\phi_{p^*}(L) = \frac{1}{2}$. When $L \rightarrow \infty$ $p^*(L) \rightarrow p_c$

$$\text{For } d=1 \quad \phi_{p^*}(L) = e^{-L/(1-p^*)} = \frac{1}{2}$$

$$\Rightarrow 1 - p^* \equiv p_c - p^* \approx \frac{1}{L}$$

* How p^* will behave in d - dimensional percolation?

p_c for Finite Systems

$\phi_p(L)$: the probability for percolation in a d-dimensional lattice of size L with prob. p .

Since $\phi_p(\infty) = 1$ for $p > p_c$ and $\phi_p(\infty) = 0$ for $p < p_c$,

we expect for $\phi_p(L)$ $y=0$ (due to step function) and

$$\phi_p(L) = f\left((p - p_c)L^{1/\nu}\right) \equiv f(x)$$

$f(x)$ increases from 0 to 1 for x increasing from $-\infty$ to ∞

The quantity $\frac{d\phi}{dp}$ is the probability that percolation occurs (for the first time) between p and $p+dp$ per unit dp .

p_c in Finite Systems

The prob. that at p percolation occur, for the first time :

(prob. that p is p_c)
$$\frac{d\phi}{dp} = L^{1/\nu} f' \left((p - p_c) L^{1/\nu} \right)$$

For $L \rightarrow \infty$
$$\frac{d\phi}{dp} \rightarrow \delta(p - p_c)$$


The average critical concentration \bar{p} as a function of L is given by

$$\bar{p} = \int_0^1 p \frac{d\phi}{dp} dp$$

\bar{p} can be easily calculated by simulation for different L .

From the form of $\frac{d\phi}{dp}$ and since $\int_0^1 \frac{d\phi}{dp} dp = 1$ it follows

$$\bar{p} - p_c = C \cdot L^{-1/\nu} \quad C \equiv \int_{-\infty}^{\infty} z f'(z) dz \quad z \equiv (p - p_c) L^{1/\nu}$$



p_c for Finite Systems

$$\bar{p} - p_c = CL^{-1/\nu} \quad (1)$$

In some symmetrical cases such as triangular lattice $f'(z)$ is symmetric around $z=0$ and thus $C \equiv \int_{-\infty}^{\infty} zf'(z)dz = 0$ and there is no correction! $\bar{p} = p_c$

Eq. (1) helps to determine in simulations both p_c and ν


Plot the measured \bar{p} as a function of $L^{-1/\nu}$

Trying several values of ν when $\nu' = \nu$ one gets a straight line which also determine p_c

Example $d=1$: $\frac{d\phi}{dL} = Lp^{L-1}$

$$\bar{p} = \frac{L}{L+1}$$

$$p_c - \bar{p} = 1 - \bar{p} = \frac{1}{L+1} \quad \text{as in Eq.(1)}$$




p_c for Finite Systems

$$\bar{p} - p_c = CL^{-1/\nu} \quad (1)$$

- Every $\phi_{p^*}(L) = \text{const.}$ leads to $p^* - p_c = c_1^* L^{-1/\nu}$

- Also $\left. \frac{d\phi}{dp} \right|_{p^*} = \max$ (p^* is an inflection point) leads to $p^* - p_c = c_2^* L^{-1/\nu}$



- The maximum of the mean finite clusters size $S(p)$ approach to p_c as $L^{-1/\nu}$
 - Eq.(1) is valid for every percolation property.
 - The above conclusions are correct also for other critical phenomena used earlier.
- $p-p_c$ is replaced by $T-T_c$

The width of transition in finite systems

Define width of transition $\Delta(L,p)$

$$\Delta^2 = \int (p - \bar{p})^2 \frac{d\phi}{dp} dp = \overline{p^2} - \bar{p}^2$$

$$\propto L^{-2/\nu}$$

$$\Delta \sim L^{-1/\nu} \quad (2)$$

Δ can be determined from MC simulations and thus evaluate ν

Here the knowledge of p_c is not needed!

To determine p_c one can calculate

$$\bar{p} - p_c \propto \Delta$$

Eq. (2) will be useful for optimization problems!!